

Clicker 5 Mac Network Installation

1. Prepare the Network Server

Create a folder named '**Crick**' on the server (this will be used for shared user files). Ensure the folder has Read/Write access to everyone so all your client computers can access it over the network.


2. Run the Clicker 5 Network Installer

The Clicker 5 Server Installer creates a folder named 'Clicker5' in the '**Crick**' folder on your server, which contains:

- An '**Examples**' folder containing example activities
- The Clicker 5 Quick Tour
- The Clicker 5 Home Grid
- A client installer, which you use to install Clicker 5 on the client computers

To install these on your server:

- a) Connect to your network server from a client computer.
- b) Insert the Clicker 5 CD into the client computer.
- c) Double-click the Clicker 5 Network Installer icon.



- d) Enter your serial number and activation key as they appear on your blue license document, and then click **Continue**.

User Information

Clicker 5

Please type your serial number and activation key. You can find these numbers printed on the blue and white 'License Document' supplied with Clicker.


Full Name :

Serial Number :

Activation Key :

2. Run the Clicker 5 Network Installer CONTINUED


e) Read the license agreement and select **I Accept** if you agree to the terms.



f) Select the 'Crick' folder on the server (ie. **aft://MacServer.local./crick**) when prompted and select **Choose**.

g) Click **Continue** to finish installation on the server.

h) Once installed you will see the message "The software was successfully installed".



3. Run the Clicker 5 Client Installer from the Mac client

This installs, on each client computer:

- **The Clicker 5 application** (in the 'Applications' folder)
- **The Crick Picture Library** (in a 'Pictures' folder within the 'Application Support' folder)

Information is saved onto the client so Clicker 5 knows the location of the 'Clicker5' folder on the server.

This folder is used as:

- **The default location for opening files**
- **The default location for saving files**

To install Clicker 5 on each client computer:

1. On the client computer, browse to the '**Crick Software**' folder on your server.
2. Double-click **Clicker 5 Installer.dmg**.
3. Double-click **Clicker 5 Installer.mpkg**.
4. Click **Continue** to start installation.
5. Follow the on-screen instructions.
6. Repeat this on each client computer on which you wish to install Clicker 5.

You can also deploy the **Clicker 5 Installer.mpkg** file via Apple Remote Desktop (please visit the Apple website for information on deploying software via Apple Remote Desktop).